



## Analysis of Non-Human Primate Pancreatic Islet Oxygen Consumption

Joseph M. Elsagr<sup>1</sup>, Charles Deeter<sup>2</sup>, Valerie Ricciardi<sup>3</sup>, Maureen Gannon<sup>1,4,5,6</sup>

<sup>1</sup>Department of Molecular Physiology and Biophysics, Vanderbilt University

<sup>2</sup>Agilent Technologies

<sup>3</sup>Department of Biological Sciences, Vanderbilt University

<sup>4</sup>Department of Veterans Affairs Tennessee Valley

<sup>5</sup>Department of Medicine, Vanderbilt University Medical Center

<sup>6</sup>Department of Cell and Developmental Biology, Vanderbilt University

### Abstract

The measurement of oxygen consumption in spheroid clusters of cells, such as *ex vivo* pancreatic islets, has historically been challenging. We demonstrate the measurement of islet oxygen consumption using a 96-well microplate designed for the measurement of oxygen consumption in spheroids. In this assay, spheroid microplates are coated with a cell and tissue adhesive on the day prior to the assay. We utilize a small volume of adhesive solution to encourage islet adherence to only the bottom of the well. On the day of the assay, 15 islets are loaded directly into the base of each well using a technique that ensures optimal positioning of islets and accurate measurement of oxygen consumption. Various aspects of mitochondrial respiration are probed pharmacologically in non-human primate islets, including ATP-dependent respiration, maximal respiration, and proton leak. This method allows for consistent, reproducible results using only a small number of islets per well. It can theoretically be applied to any cultured spheroids of similar size.

### Keywords

Developmental Biology; Issue 154; islet; oxygen consumption; spheroid; mitochondria;  $\beta$  cell; pancreas; non-human primate

### Introduction

In order to maintain normal blood glucose levels, the pancreatic  $\beta$  cell must sense elevations in glucose and secrete insulin accordingly. The coupling of insulin secretion with glucose levels is directly linked to glucose metabolism and the production of ATP through

---

Correspondence to: Maureen Gannon at [maureen.gannon@vumc.org](mailto:maureen.gannon@vumc.org).

Disclosures

The authors have nothing to disclose.

Video Link

The video component of this article can be found at <https://www.jove.com/video/60696/>

mitochondrial oxidative phosphorylation. Thus, mitochondria play a critical role in stimulus-secretion coupling<sup>1</sup>. Assessing  $\beta$ -cell mitochondrial function can reveal defects that lead to impaired insulin secretion. The secretion of glucagon by pancreatic  $\alpha$  cells is also closely tied to mitochondrial function<sup>2</sup>. Although immortalized islet cell lines have proven useful for some types of assays, the physiology of these cells does not accurately recapitulate whole islet function, as illustrated by the potentiation of insulin secretion by glucagon<sup>3,4</sup> and the inhibition of glucagon secretion by insulin/somatostatin<sup>5,6</sup> in intact islets. This demonstrates the need for measuring oxygen consumption using whole, intact islets.

Techniques for the measurement of islet cell respirometry have evolved over time, from the use of oxygen-sensitive fluorescent dyes<sup>7</sup> to solid-state sensors that directly measure oxygen consumption<sup>8</sup>. Initially designed for monolayer, adherent cells, commonly used cell culture plate systems have proven to be ineffective for pancreatic islets. As islets do not naturally adhere to the wells, they are prone to being pushed to the periphery of the culture well resulting in inaccurate measurement of oxygen consumption<sup>9</sup>. To combat this problem, specialized 24-well plates with a central depression that could contain islets were developed<sup>9</sup>. However, the 24-well plate system was limited by the large number of islets required (50–80 per well) and the number of conditions that could be tested simultaneously<sup>10</sup>. The recent development of 96-well microplates designed specifically for extracellular flux analysis in spheroids has overcome these barriers, enabling the measurement of islet respirometry with 20 or fewer islets per well<sup>10</sup>.

Here, we demonstrate the use of this system to measure oxygen consumption in islets from the Japanese macaque (*Macaca fuscata*), an animal model with similar islet biology to humans<sup>11,12</sup>. In this protocol, 15 macaque islets are analyzed per well. In our hands, 15 islets per well produced higher baseline oxygen consumption than fewer islets, with robust activation and repression of respiration in response to pharmacologic manipulation. We highlight the steps to prepare for the assay, an effective method for consistent loading of islets at the center of each well, and common challenges when performing this assay.

## Protocol

### 1. Preparation of Microplate and Sensor Cartridge on the Day Prior to Running the Assay

Islets were isolated from three year old Japanese macaques as previously described<sup>13</sup>. This method is very similar to that used to isolate human islets from cadaver donors, but differs from mice, in which pancreata are often inflated with collagenase solution while the animal is under sedation and prior to organ removal. Islet retrieval was conducted in accordance with the guidelines of the Institutional Animal Care and Use Committee (IACUC) of the Oregon National Primate Research Center (ONPRC) and Oregon Health and Science University and were approved by the ONPRC IACUC. The ONPRC abides by the Animal Welfare Act and Regulations enforced by the United States Department of Agriculture (USDA) and the Public Health Service Policy on Humane Care and Use of Laboratory Animals in accordance with the Guide for the Care and Use of Laboratory Animals published by the National Institutes of Health.

#### 1. Preparation of Spheroid Microplate

1. Prepare 3 mL of a 0.1M solution of sodium bicarbonate. Filter sterilize the solution. We utilized a 0.45  $\mu\text{m}$  filter (Table of Materials).
2. In a cell culture hood, add 200  $\mu\text{L}$  of cell and tissue adhesive (Table of Materials) to 2.8 mL of 0.1M sodium bicarbonate. Then, add 20  $\mu\text{L}$  of this solution to the bottom of each well of the 96-well spheroid microplate (Table of Materials). Ensure that air bubbles are removed from the pipet tip and only the bottom of the plate is covered. Coating of the microplate prevents islets from moving up the sides of the wells when drugs are added and mixed into the well during the assay.

**NOTE:** It is only necessary to coat as many wells as will be used for islets when the assay is run. If only a few wells will be used, the cell adhesive solution can be scaled down appropriately. The cell adhesive used in the assay is a formulated protein solution extracted from the marine mussel. Alternatively, microplate wells can be coated with 20  $\mu\text{L}$  of 100  $\mu\text{g}/\text{mL}$  poly-D-lysine.

3. Incubate the plate in a 37  $^{\circ}\text{C}$ , non- $\text{CO}_2$  incubator for one hour.
  4. In a sterile environment, aspirate cell adhesive solution from the plate. Wash each well two times with 400  $\mu\text{L}$  of 37  $^{\circ}\text{C}$  sterile water using a multichannel pipet. Allow to air dry.
  5. After 30–40 minutes, cover the plate and store overnight at 4  $^{\circ}\text{C}$ .
2. Hydration of the Sensor Cartridge
    1. In a sterile environment, open the sensor cartridge package (Table of Materials) and remove the contents. Place the sensor cartridge upside down next to the utility plate.
    2. Fill each well of the utility plate with 200  $\mu\text{L}$  sterile water and lower the sensor cartridge back into the utility plate. Place assembled sensor cartridge and utility plate in a 37  $^{\circ}\text{C}$ , non- $\text{CO}_2$  incubator overnight.
  3. Preparation of Calibrant
    1. Aliquot 25 mL of calibrant (Table of Materials) into a 50 mL conical tube. Place tube in a 37  $^{\circ}\text{C}$ , non- $\text{CO}_2$  incubator overnight.

## 2. Protocol for Media Preparation, Loading of Islets, and Loading of Sensor Cartridge on the Day of Assay

1. Preparation of media
  1. To 48.5 mL of base media (minimal DMEM, see Table of Materials), add 500  $\mu\text{L}$  each of 1 mM sodium pyruvate and 2 mM glutamine. Additionally, add 496  $\mu\text{L}$  of 200 mg/ml glucose (final concentration of glucose in the media is 5.5 mM).

**NOTE:** Baseline glucose concentration was kept constant for these experiments. However, glucose can also be used to stimulate respiration in addition to the pharmacologic manipulations described below<sup>10</sup>.

2. Confirm that the pH is 7.4  $\pm$  0.1, adjusting if necessary.
2. Preparation of sensor cartridge
  1. Take sensor cartridge out of incubator, remove sensor cartridge lid, and dump out water from wells. Place 200 mL of pre-warmed calibrant into each well and replace sensor cartridge lid.
  2. Place sensor cartridge back in incubator for about 1 hour (until needed).
3. Preparation of drugs for mitochondrial stress assay
  1. Open the stress test kit (Table of Materials) and remove the contents. Make up stock and working solutions for Oligomycin, Carbonyl cyanide-4-(trifluoromethoxy)phenylhydrazone (FCCP), and Rotenone/Antimycin A (AA) as follows.
    1. Oligomycin: add 630  $\mu$ L of assembled media to tube to make 100  $\mu$ M stock. Then, dilute to 45  $\mu$ M with media to obtain port concentration (final well concentration after injection will be 4.5  $\mu$ M)
    2. FCCP: add 720  $\mu$ L of assembled media to tube to make 100  $\mu$ M stock. Dilute to 10  $\mu$ M with media to obtain port concentration (final well concentration will be 1  $\mu$ M)

**NOTE:** BSA and/or FBS should not be added to media, as this can affect the action of mitochondrial uncouplers<sup>14</sup>.
  3. Rotenone/AA: add 540  $\mu$ L of assembled media to tube to make 50  $\mu$ M stock. Dilute to 25  $\mu$ M with media to obtain port concentration (final well concentration will be 2.5  $\mu$ M)

**NOTE:** The above concentrations have produced consistent results in our hands. Additional FCCP led to no further increase in respiration. However, drug concentrations may need to be adjusted depending on islet size, and especially with islets from different species or non-islet spheroids. For reference, the average diameter of a non-human primate islet is about 150  $\mu$ m<sup>15</sup>.
4. Preparation of spheroid plate and transfer of islets
  1. Hand-pick pancreatic islets into a 60 mm x 15 mm cell culture dish containing assembled media to obtain near 100% purity.

**NOTE:** Islets should appear rounded, with a clearly defined periphery, and appear denser than exocrine tissue contaminants. Avoid islets that appear damaged or frayed. In this experiment, islet size was not directly

measured, although we attempted to pick islets of approximately equivalent size for each well and sample.

2. Load each well of spheroid microplate with 175  $\mu\text{L}$  of assembled media using a multichannel pipette.
3. Using a P20 pipette set to 15  $\mu\text{L}$ , aspirate 15 islets from cell culture dish. Islets should be visible in the pipette tip to the naked eye.
4. To transfer islets to spheroid microplate, lower pipette tip to the bottom of the well, barely lift up, and slowly pipette out a very small volume ( $\sim 5 \mu\text{L}$ ). Confirm that all islets have left the pipette tip. Each well should receive 15 islets. Occasionally check spheroid microplate under the microscope to verify that islets are at the bottom of each well rather than stuck to the sides.

**NOTE:** Avoid loading the corner wells with islets. Oxygen and pH flux out of the plastic can occur during the assay, and this is exacerbated in the four corner wells.

5. Once all islets have been transferred to the spheroid microplate, incubate the microplate in a 37  $^{\circ}\text{C}$ , non- $\text{CO}_2$  incubator while completing the steps below.
5. Loading the sensor cartridge and running the assay
    1. Remove sensor cartridge from incubator. Ports A-C for each well must be loaded with either drug or media. Wells containing islets and the four corner wells should be loaded with drug. Non-corner wells without islets should be loaded with media. Port D can be left empty. Load port A (top left of each sensor) with 20  $\mu\text{L}$  of oligomycin or media. Load port B (top right) with 22  $\mu\text{L}$  of FCCP or media. Load port C (bottom left) with 25  $\mu\text{L}$  of Rotenone/AA or media.
    2. Program an extracellular flux analyzer assay for a 30 minute baseline respiration period (5 cycles of 3 minute mix, 3 minute measure), 42 minute oligomycin measurement period (7 cycles of 3 minute mix, 3 minute measure), 30 minutes FCCP (5 cycles of 3 minute mix, 3 minute measure), and 30 minutes Rotenone/AA (5 cycles of 3 minute mix, 3 minute measure).
    3. Run the assay and follow instructions on screen for calibrating the sensor and inserting the microplate.

## Representative Results

To load islets into microplate, 15 islets should be aspirated in 15  $\mu\text{L}$  of media, as shown in Figure 1A. Islets will naturally settle toward the bottom of the pipet tip within a few seconds. Then, the pipet tip is lowered to the bottom of the well. The tip is very slightly lifted, and a small volume (about 5  $\mu\text{L}$ ) is pipetted out along with the islets. This technique

results in consistent placement of islet at the bottom of the microplate well (Figure 1B) allowing for accurate oxygen consumption measurements.

Figure 2 shows representative results by individual well for oxygen consumption throughout the assay. This particular experiment demonstrates what can happen when wells are loaded poorly, with many islets stuck up on the sides of the well rather than at the bottom of the well. This can be caused by pipetting too much media into the well after the islets have already been pipetted out of the tip. The flow of additional media pushes the islets out of the bottom of the well. When this happens, the baseline level of oxygen consumption will be very low, and this well will show little to no response to FCCP. The bolded line in Figure 2 demonstrates this phenomenon.

Figure 3 shows a different experiment in which most wells did show significant baseline respiration and response to drugs. However, two wells (with bolded lines) showed no response to rotenone/AA. This suggests that the drug was not properly released into the well. In this case, as with cases of no basal oxygen consumption, these wells can be excluded from further analysis.

Figure 4 shows the results of a successful assay. Here we show an example of summary data from a separate experiment in which wells were properly loaded with islets and correctly injected with drugs. ATP-dependent mitochondrial oxygen consumption was effectively inhibited by oligomycin, maximal respiration-well above basal levels-was induced by FCCP, and mitochondrial respiration was completely shut down-below oligomycin levels-by inhibition of the electron transport chain with rotenone/AA.

## Discussion

The study of islet oxygen consumption has previously been hampered by the spherical shape of islets, their lack of adherence to culture surfaces, and the number of islets required per well. In this protocol, we highlight the efficacy of the 96-well spheroid microplate for measuring islet oxygen consumption on a small number of islets and demonstrate a technique for handling and loading islets which is technically feasible and produces consistent results.

In order for islets to adhere to the bottom of the microplate and be unperturbed during mixing steps throughout the assay, the 96-well microplate is coated with a cell adhesive solution the day before the assay. While this is generally beneficial, if islets are not loaded properly they are liable to stick to the side of the well rather than the bottom, thus affecting or precluding accurate measurement. To combat this, we recommend coating wells with a very small volume of adhesive solution-only 20  $\mu$ L. Additionally, the pipetting technique we demonstrate ensures that islets are loaded to the bottom of the well and not pushed up the sides by the flow of additional media.

The 96-well spheroid microplate has overcome previous limitations of measuring islet oxygen consumption, including the high number of islets required and the number of conditions that can be tested simultaneously. Indeed, a recent study<sup>10</sup> demonstrated the use of this system with a single human islet per well. However, measurement of oxygen

consumption using single islets resulted in very low basal measurements of oxygen consumption, which were significantly above background in only the largest islets (diameter above 290  $\mu\text{m}$ ). NHP islets tend to be smaller than human islets, with an average diameter of only 150  $\mu\text{m}$ <sup>15</sup>. In our hands, 15 NHP islets per well showed higher baseline and a more responsive profile during the cell stress test than fewer islets. We also tested five and ten islets per well, but found that basal oxygen consumption and signal to noise were significantly reduced.

In addition to the ability to use a low number of islets per well, the 96-well microplate allows for the testing of multiple different conditions at once. This is beneficial in cases where islets are treated with different compounds or genetically manipulated. However, when comparing groups of human or non-human primate islets that come from different sources (e.g., diabetic versus non-diabetic islets), samples are often received on different days. Thus, in these cases it is not possible to take full advantage of this system.

In order to quantify various aspects of mitochondrial oxygen consumption, we manipulated different aspects of respiration pharmacologically. Drug concentrations used were based on a previous study in human islets<sup>10</sup>. The dose of FCCP was optimized to induce maximal mitochondrial respiration in our hands. Specifically, the concentration of oligomycin was 4.5  $\mu\text{M}$ , FCCP was 1  $\mu\text{M}$ , and rotenone/AA was 2.5  $\mu\text{M}$ . However, these concentrations likely need to be calibrated for different applications of this protocol.

The data produced can be either analyzed directly or normalized using a number of methods. In this experiment, equal numbers of islets of similar sizes were used for each sample, and data was not normalized by cell number or islet size, which can be difficult to directly quantify. An alternative method of normalization is by total cellular protein, which involves lysing cells after the assay is performed and quantifying protein levels. Data can also be normalized to basal respiration levels. This may be informative in certain cases, such as the quantification of reserve capacity as a percentage of basal levels. However, with these normalization methods and others, information can be lost during normalization as previously described<sup>16</sup>.

The system described here provides a unique tool to better understand islet physiology. Indeed, the importance of oxygen consumption in islet health is illustrated by the observation that islet oxygen consumption rates are closely tied with islet health and the probability of successful islet transplantation<sup>17</sup>. This system provides an excellent platform for consistent quantification of islet oxygen consumption which can, in theory, also be applied to any similarly-sized cultured spheroids.



## Acknowledgments

The authors would like to acknowledge the Vanderbilt High Throughput Screening Core for the use of their facilities, Agilent Biotechnologies, Dr. Paul Kievit (Oregon Health and Science University) for non-human primate islet isolations, and Eric Donahue (Vanderbilt University) for assistance with Figure 1. J.M.E. was supported by NIGMS of the National Institutes of Health under award number T32GM007347. M.G. was supported by the NIH/NIDDK (R24DK090964-06) and the Department of Veterans Affairs (BX003744).


## References

1. Mulder H Transcribing  $\beta$ -cell mitochondria in health and disease. *Molecular Metabolism*. 6 (9), 1040–1051 (2017). [PubMed: 28951827]
2. Maechler P, Wollheim CB Mitochondrial signals in glucose-stimulated insulin secretion in the beta cell. *The Journal of Physiology*. 529 (Pt 1), 49–56 (2000). [PubMed: 11080250]
3. Curry DL Glucagon Potentiation of Insulin Secretion by the Perfused Rat Pancreas. *Diabetes*. 19 (6), 420 (1970). [PubMed: 4912049]
4. Song G, Pacini G, Ahrén B, D'Argenio DZ Glucagon Increases Insulin Levels by Stimulating Insulin Secretion Without Effect on Insulin Clearance in Mice. *Peptides*. 88, 74–79 (2017). [PubMed: 28012858]
5. Vergari E et al. Insulin inhibits glucagon release by SGLT2-induced stimulation of somatostatin secretion. *Nature Communications*. 10 (1), 139 (2019).
6. Watts M, Ha J, Kimchi O, Sherman A Paracrine regulation of glucagon secretion: the  $\beta/\alpha/6$  model. *American Journal of Physiology-Endocrinology and Metabolism*. 310 (8), E597–E611 (2016). [PubMed: 26837808]
7. Sweet IR et al. Continuous measurement of oxygen consumption by pancreatic islets. *Diabetes Technology & Therapeutics*. 4 (5), 661–672 (2002).
8. Agilent Technologies. Agilent Seahorse XF Instruments Overview and Selection Guide. <https://www.agilent.com/en/products/cell-analysis/seahorse-xf-instruments-selection-guide> (2019).
9. Wikstrom JD et al. A novel high-throughput assay for islet respiration reveals uncoupling of rodent and human islets. *PLoS One*. 7 (5), e33023 (2012). [PubMed: 22606219]
10. Taddeo EP et al. Individual islet respirometry reveals functional diversity within the islet population of mice and human donors. *Molecular Metabolism*. 16, 150–159 (2018). [PubMed: 30098928]
11. Conrad E et al. The MAFB transcription factor impacts islet alpha-cell function in rodents and represents a unique signature of primate islet beta-cells. *American Journal of Physiology--Endocrinology and Metabolism*. 310 (1), E91–E102 (2016). [PubMed: 26554594]
12. Steiner DJ, Kim A, Miller K, Hara M Pancreatic islet plasticity: interspecies comparison of islet architecture and composition. *Islets*. 2 (3), 135–145 (2010). [PubMed: 20657742]
13. Elsakr JM et al. Maternal Western-style diet affects offspring islet composition and function in a non-human primate model of maternal over-nutrition. *Molecular Metabolism*. (2019).
14. Soutar MPM et al. FBS/BSA media concentration determines CCCP's ability to depolarize mitochondria and activate PINK1-PRKN mitophagy. *Autophagy*. 1–10 (2019).
15. Hirshberg B et al. Pancreatic Islet Transplantation Using the Nonhuman Primate (Rhesus) Model Predicts That the Portal Vein Is Superior to the Celiac Artery as the Islet Infusion Site. *Diabetes*. 51 (7), 2135–2140 (2002). [PubMed: 12086943]
16. Divakaruni AS, Paradyse A, Ferrick DA, Murphy AN, Jastroch M Analysis and interpretation of microplate-based oxygen consumption and pH data. *Methods in Enzymology*. 547, 309–354 (2014). [PubMed: 25416364]
17. Papas KK et al. Islet Oxygen Consumption Rate (OCR) Dose Predicts Insulin Independence in Clinical Islet Autotransplantation. *PLoS One*. 10 (8), e0134428 (2015). [PubMed: 26258815]






**Figure 1: Pipetting technique for loading islets into microplate.** (A) Approximately 15 islets (red arrow) pipetted with 15  $\mu$ L of media. (B) Islets centered at the bottom of the spheroid microplate.




**Figure 2: Well-to-well variability due to difference in islet loading.**  
Wells loaded improperly (bold blue line) show little to no basal oxygen consumption and minimal response to cell stress test drugs.



**Figure 3: Failure of drug injection.**

Two wells (bold blue lines) were not injected with rotenone/AA and show no significant decrease in oxygen consumption.



**Figure 4: Averaged data across all wells in an experiment after exclusion of poorly loaded or injected wells.**

Average oxygen consumption throughout the cell stress test assay in a separate experiment including 16 technical replicates. Error bars show standard deviation for n = 16 wells.

Name	Company	Catalog Number	Comments
Cell culture dish, 60 mm X 15 mm style	Corning	430166	
Cell-Tak Cell and Tissue Adhesive	Corning	354240	
Conical tube, 50 mL	Falcon	352070	
Dextrose anhydrous	Fisher Scientific	BP350-1	For glucose solution, 200 mg/ml, sterile filtered
Disposable reservoirs (sterile), 25 ML	Vistalab	3054-1033	for loading multichannel pipet
EZFlow Sterile 0.45 µm PES Syringe Filter, 13 mm	Foxx Life Sciences	371-3115-OEM	
L-glutamine	Gibco	25030-081	200 mM (100x)
Multichannel pipette tips	ThermoFisher Scientific	94410810	
Multichannel pipette, 15-1250 µL	ThermoFisher Scientific	4672100BT	Recommended
P20, P200, and P1000 pipettes	Eppendorf	2231000602	
pH Probe	Hanna Instruments	HI2210-01	
Pipette tips, 20 µL, 200 µL, 1000 µL	Olympus	24-404, 24-412, 24-430	
Seahorse XF Base Media	Agilent	103334-100	
Seahorse XF Cell Mito Stress Test Kit	Agilent	103015-100	Includes Oligomycin, FCCP, and Rotenone/Antimycin A
Seahorse XFe96 Analyzer	Agilent	S7800B	Including prep station with 37 °C non-CO2 incubator
Seahorse XFe96 Spheroid Fluxpak Mini	Agilent	102905-100	Includes sensor cartridge, spheroid microplate, and calibrant
Sodium bicarbonate	Fisher Scientific	BP328-500	
Sodium pyruvate	Gibco	11360-070	100 mM (100x)
Stereo Microscope	Olympus	SZX9	
Syringe (sterile), 5 mL	BD	309603	For sterile filtration
Water (sterile)	Sigma	W3500-500mL	